

# Logic Flow of the Quickstart

for comment, question, addition, subtraction, wording, rewording

## **Title: Welcome to the Commotion Quick Start wizard!**

Congratulations! You have a Commotion node and are ready to join a network or start a new one. This wizard will guide you through the setup. The setup process should take about 10 minutes.

You can still change settings after setup is complete. To change settings later, connect your computer to the node with an ethernet cable and log on to: xxx

First, the wizard will scan to see if there are any existing mesh networks in your area.

## Title: Joining Existing Networks

It looks like there is a mesh network to join! Select one or more networks below, or create a new mesh network.

network 1  
network 2  
network 3

Join this [these] network[s] >>

No networks were found.  
[instead of join the network have a "Try Again"]

Join other network[s] >>

Create my own network >>

## Title: Network Security Settings

This network requires a key file and password. These should be provided by your network administrator.

Upload Key

Password:

\*\*\*\*\*

Next >>

<< Back

<< Start Over

## Title: Using a Settings File

### Do you have a settings file?

Your network administrator may have provided a settings file.

If you have a settings file, please upload it below. Or, you can proceed without it..

Browse...

Upload & Continue >>

Continue >>

<< Back

<< Start Over

## Title: Using an existing Network Setup

You may use one of these default configurations, or create your own configuration.

[To connect with the selected mesh network[s], your Network Setup must include X, Y, Z.]

- ☐ Config 1: xxx
- ☐ Config 2: xxx

Next >>

Configure Manually >>

<< Back

<< Start Over

## Title: Network Security Settings

This network configuration requires a key and password.

Remember, other nodes will have to use this key to connect to this mesh network.

Upload a key

If this is a new network, please generate a key.

Generate a key

Please enter the network password.

\*\*\*\*\*

<< Select a different configuration

<< Start Over

Next >>

**Title: Mesh Network Name (If this is a new network)**

What would you like to name your mesh network?

(This will be the first part of the name people will see when they search for your wireless network.)

**[Title:] Please name your Node**

What would you like to name your node?

(This will be the second part of the name people will see when they search for your wireless network.)

Choose a name that is 5-12 characters. You can use numbers, letters & special characters. The name must be unique in the network. You can change the node name later by logging into the node administration page.

The wireless node name will be visible to others as:

**[DISPLAY\_NAME\_AS\_TYPED]\_[NODE\_NAME\_PLACEHOLDER]**

<< Back

<< Start Over

Next >>

## **Title: Your Network**

The name of your mesh network is:

---

Your node name is:

---

When people connect to your node wirelessly, they will connect using this name:

---

After configuring your node, you can change the node name on the node administration page.

<< Back

<< Start Over

Continue >>



## **Title: Please set an Administrator password**

Enter an "administrator" password for your node.

You will use this password to change your node's settings later. It is important to set a strong password, and keep it secret so others cannot change your settings.

Choose a password that is at least 10 characters. It must include at least one number and one capital letter. Using special characters such as !, \$, %, &, or @ is also recommended.

It is not possible to recover this password for your node. If you lose or forget this password, you must reinstall Commotion and set up your node from scratch.

When you click "Next," your node will apply all settings. This will take about two minutes.

<< Back

<< Start Over

Next >>

**Title: Your node is configuring**

Please wait while your node updates its settings. The node will restart during this process. This should take approximately two minutes.

The update will be complete in [TIMER]

## **Title: Setup is complete!**

You have completed the Commotion quickstart. Check below to see if your node is connected to any other nodes in the area.

You are connected to the X network with Y neighbors.

[Or] Your node is not currently connected to the mesh.

There may be a configuration problem, or other wireless signals may be blocked.

<< There is a problem. Start Over

Finish. Go to the Node admin>>

**Welcome to [NETWORK\_NAME], powered by Commotion!**

Please log in to administer this node, [NODE\_NAME], using the node admin password you generated during quickstart.

username:

password:

# **Manual Configuration Steps:**

**Title: Mesh Network Name (If this is a new network)**

What would you like to name your mesh network?

(This will be the first part of the name people will see when they search for your wireless network.)

**Please name your Node**

What would you like to name your node?

(This will be the second part of the name people will see when they search for your wireless network.)

Choose a name that is 5-12 characters. You can use numbers, letters & special characters. The name must be unique in the network. You can change the node name later by logging into the node administration page.

The wireless node name will be visible to others as:

**[DISPLAY\_NAME\_AS\_TYPED]\_[NODE\_NAME\_PLACEHOLDER]**

Next >>

## **Title: Please set an Administrator password**

Enter an "administrator" password for your node.

You will use this password to change your node's settings later. It is important to set a strong password, and keep it secret so others cannot change your settings.

Choose a password that is at least 10 characters. It must include at least one number and one capital letter. Using special characters such as !, \$, %, &, or @ is also recommended.

It is not possible to recover this password for your node. If you lose or forget this password, you must reinstall Commotion and set up your node from scratch.

When you click "Next," your node will apply all settings. This will take about two minutes.

<< Back

Next >>

## Title: Setup Wireless Connection sharing

Would you like to allow anyone to connect to your node?

Yes [ X ]

No [ X ]

Generate or upload a key before you set a password. If you are connecting to an existing network, your network administrator should provide the network key.

Generate a key for me

Upload a key

Set a password to access this node. Others will need this password to connect to this node. This password is different from your node administration password.

Password:

\*\*\*\*\*

Next >>



## Title: Sharing your Internet Connection

Are you planning to connect a cable between this Router and your home or business Internet connection?

Yes

No. Skip this step >>

Internet access will be available to those that connect to the mesh.  
You may choose to advertise it to the mesh, or keep it hidden.

Please advertise my Internet access. >>

Please don't advertise my Internet access. >>  
(Note that access will still be available, just not advertised)

Continue >>

## Title: Setup a Splash Page

Would you like people connecting to your node to first see a splash page on their web browser?

This is the only way to ask people connecting to the node to agree to a Community Standards agreement or Terms of Service.

Yes

No. Skip this step >>

Please provide the following information.

Continue >>

### **Title: Setup Mesh Application Advertising**

Would you like to advertise mesh applications to people connected to your node?

You will be alerted when new applications are available and need approval.

Yes >>

No. Skip this step >>

**Title: Your node is configuring**

Please wait while your node updates its settings. The node will restart during this process. This should take approximately two minutes.

The update will be complete in [TIMER]

## **Title: Setup is complete!**

You have completed the Commotion quickstart. Check below to see if your node is connected to any other nodes in the area.

You are connected to the X network with Y neighbors.

[Or] Your node is not currently connected to the mesh.

There may be a configuration problem, or other wireless signals may be blocked.

<< There is a problem. Start Over

Finish. Go to the Node admin>>

**Welcome to [NETWORK\_NAME], powered by Commotion!**

Please log in to administer this node, [NODE\_NAME], using the node admin password you generated during quickstart.

username:

password: